

1-1. SiS 630 Video Driver

<i>Operation System</i>	<i>Support Font</i>	<i>Driver Version</i>	<i>PC99 LOGO</i>	<i>File Name</i>
Windows 98 (E)	English	1.06.51	Not yet (1.03 Passed)	W98_R106_51.zip
Windows 98 (J)	Japanese			
Windows NT 4.0 (E)	English	1.06.51	Not yet (1.03 Passed)	NT4_R106_51.zip
Windows NT 4.0 (J)	Japanese			
Windows 2000 (E)	English	1.06.51	Not yet (1.03 Passed)	W2K_R106_51.zip
Windows 2000 (J)	Japanese			


Note: 1. To install Windows 98 drivers, please run SETUP.EXE in this directory.

2. For Windows NT 4.0 Installation:

- a. Click "Start" menu and select Control Panel from Settings group.
- b. Select Display icon, then select Settings of Display Properties.
- c. Select Display Type, then select Change from the Adapter Type area.
- d. Select Have Disk of Change Display.
- e. and place the S/W Driver CD into CDROM Drive.
- f. When the "Install from Disk" dialog box appears, type the directory storing the drivers and click "OK".
- g. Complete the installation; you must now restart Windows NT 4.0.

3. For Windows 2000 Driver Installation:

- a. First run \VGA\Win2000\SETUP.EXE,
- b. Then run \VGA\Win2000\AGP\SETUP.EXE

 : The gray item means "New" driver.

1-2. SiS 7018 Audio Driver

<i>Operation System</i>	<i>Support Font</i>	<i>Driver Version</i>	<i>PC99 LOGO</i>	<i>File Name</i>
Windows 98 (E)	English	1.04	Passed	SA104.exe
Windows 98 (J)	Japanese			
Windows NT 4.0 (E)	English	1.04	Passed	SA104.exe
Windows NT 4.0 (J)	Japanese			
Windows 2000 (E)	English	1.04	Passed	SA104.exe
Windows 2000 (J)	Japanese			


Note: 1. To install Windows 98/NT4/Win2000 drivers, please run SETUP.EXE in this directory.

2. SETUP.EXE automatically installs WDM or VxD driver for Windows 95/98 base on the O.S version:

- WDM driver is installed for Windows 98SE and
- VxD is installed for Windows 98OEM (first edition, 4.10.1998) and Windows 95.

3. To force installing VxD driver for Windows 98SE, please run "SETUP.EXE -vxd" using Windows Start->Run.

4. WDM driver support DirectX 7.0


 : The gray item means "New" driver.

1-3. SiS 900 LAN Driver

<i>Operation System</i>	<i>Support Font</i>	<i>Driver Version</i>	<i>PC99 LOGO</i>	<i>File Name</i>
Windows 98 (E) Windows 98 (J)	English	1.09	Passed	SL109.exe
Windows NT 4.0 (E) Windows NT 4.0 (J)	English	1.09	Passed	SL109.exe
Windows 2000 (E) Windows 2000 (J)	English	1.09	Passed	SL109.exe

Note: 1. To install Windows 95/98 drivers, please run SETUP.EXE in this directory.

2. Do not click "Cancel" while "New Hardware Wizard" searching for the device or drivers.

 : The gray item means "New" driver.


1-4. CD-ROM Driver for TEAC 24x

<i>Operation System</i>	<i>Support Font</i>	<i>Driver Version</i>	<i>PC99 LOGO</i>	<i>File Name</i>
DOS 6.X (E) DOS 6.X (J)	English	1.27q	-	TEAC127Q.zip

Note: 1. Please modify the CONGIF.SYS and AUTOEXEC.BAT as following,

CONFIG.SYS → add "DEVICE=TEAC_CD1.SYS /D:CDROM001"


AUTOEXEC.BAT → add "MSCDEX.EXE /D:CDROM001"

 : The gray item means "New" driver.

1-5. CD-ROM Driver for MKE 24x

<i>Operation System</i>	<i>Support Font</i>	<i>Driver Version</i>	<i>PC99 LOGO</i>	<i>File Name</i>
DOS 6.X (E) DOS 6.X (J)	English	1.9	-	MKE19.zip


Note:

 : The gray item means "New" driver.

1-6. DVD-ROM Driver for SANYO 6x (Option)

<i>Operation System</i>	<i>Support Font</i>	<i>Driver Version</i>	<i>PC99 LOGO</i>	<i>File Name</i>
DOS 6.X (E) DOS 6.X (J)	English	3.70M	-	SANYO370M.zip

Note:

 : The gray item means "New" driver.


1-7. CD-RW Driver for KME (Option)

<i>Operation System</i>	<i>Support Font</i>	<i>Driver Version</i>	<i>PC99 LOGO</i>	<i>File Name</i>
DOS 6.X (E) DOS 6.X (J)	English	1.51	-	KME151.zip

Note: 1. Please modify the CONGIF.SYS and AUTOEXEC.BAT as following,

CONFIG.SYS → add “DEVICE=KMEATAPI.SYS /D:CDROM001”

AUTOEXEC.BAT → add “MSCDEX.EXE /D:CDROM001”


 : The gray item means “ New” driver.

1-8. System BIOS Flash Update Utility

<i>Operation System</i>	<i>Support Font</i>	<i>Driver Version</i>	<i>PC99 LOGO</i>	<i>File Name</i>
DOS 6.X (E) DOS 6.X (J)	English	1.5	-	Flash15.zip

Note: 1. Please run “FLASHIT ROM-filename” without HIMEM.SYS memory manager loaded in real mode DOS.

2. Support EON EN29F002NT flash part.

 : The gray item means “ New” driver.

1-9. Save to Disk Utility

<i>Operation System</i>	<i>Support Font</i>	<i>Driver Version</i>	<i>PC99 LOGO</i>	<i>File Name</i>
DOS 6.X (E) DOS 6.X (J)	English	4.00.00	-	0VMAKFIL.exe

Note: 1. Usage: 0VMAKFIL.EXE -[?|H] | [F[V|W|#]] | [P[V|W|#]]

= Size in MB


? or H = For Usage Information

PW or FW = Forces Sector Signatures to be re-written

PV or FV = Reinitial Suspend-to-Disk

D = Add space for diagnostics partition


R = Remove Suspend To Disk Partition/Data File

 : The gray item means “ New” driver.

1-10. 3-Mode FDD Driver

<i>Operation System</i>	<i>Support Font</i>	<i>Driver Version</i>	<i>PC99 LOGO</i>	<i>File Name</i>
Windows 98 (E) Windows 98 (J)	English	1.00	-	W98_3FDD.zip
Windows NT 4.0 (E) Windows NT 4.0 (J)	English Japanese	N/A	-	
Windows 2000 (E) Windows 2000 (J)	English Japanese	Build-in	-	


Note:

 : The gray item means “New” driver.

1-11. CHICONY Keyboard Driver (9973)

<i>Operation System</i>	<i>Support Font</i>	<i>Driver Version</i>	<i>PC99 LOGO</i>	<i>File Name</i>
Windows 98 (E) Windows 98 (J)	English Japanese	2.12	Passed Not yet	KB9973E.exe KB9973J.exe
Windows NT 4.0 (E) Windows NT 4.0 (J)	English Japanese	2.12	Not yet Not yet	KB9973E.exe KB9973J.exe
Windows 2000 (E) Windows 2000 (J)	English Japanese	2.12	Not yet Not yet	KB9973E.exe KB9973J.exe


Note:

 : The gray item means “New” driver.

1-12. Logitech Mouse Driver

<i>Operation System</i>	<i>Support Font</i>	<i>Driver Version</i>	<i>PC99 LOGO</i>	<i>File Name</i>
Windows 98 (E) Windows 98 (J)	English Japanese	9.01	Not yet (8.35 passed) Not yet (8.35 passed)	Mouse901E.zip Mouse901J.zip
Windows NT 4.0 (E) Windows NT 4.0 (J)	English Japanese	9.01	Not yet (8.35 passed) Not yet (8.35 passed)	Mouse901E.zip Mouse901J.zip
Windows 2000 (E) Windows 2000 (J)	English Japanese	9.01	Not yet (8.35 passed) Not yet (8.35 passed)	Mouse901E.zip Mouse901J.zip


Note:

 : The gray item means “New” driver.

1-13. KYE Mouse Driver

<i>Operation System</i>	<i>Support Font</i>	<i>Driver Version</i>	<i>PC99 LOGO</i>	<i>File Name</i>
Windows 98 (E) Windows 98 (J)	English	4.15.00	Not yet	KYE_W98&NT4-41500.zip
Windows NT 4.0 (E) Windows NT 4.0 (J)	English	4.15.00	Not yet	KYE_W98&NT4-41500.zip
Windows 2000 (E) Windows 2000 (J)	English	5.01.00	Not yet	KYE_W2K-50100.zip

Note:

 : The gray item means “ New” driver.


1-14. SiS IDE Utility

<i>Operation System</i>	<i>Support Font</i>	<i>Driver Version</i>	<i>PC99 LOGO</i>	<i>File Name</i>
Windows 2000 (E) Windows 2000 (J)	English	1.0.0.1	-	W2KDMA.exe

Note: 1. This utility helps change SiS IDE controller running from at PIO mode to at DMA mode under Win2000 without double restart the system. After running this utility, you must have to restart your system to make this change effective.

It will not restart the system automatically. Here provides two commands to install this utility under Win2000:

- (1) Run "SiSIDE.EXE" ----> no prompt box of restart message shows, but still needs restart your system manually to make this change effective.
- (2) Run "SiSIDE.EXE /D"----> prompt box of restart message shows, but still needs restart your system manually to make this change effective.

 : The gray item means “ New” driver.

1-15. CastleNet SmartLink MDC Driver (Option)


<i>Operation System</i>	<i>Support Font</i>	<i>Driver Version</i>	<i>PC99 LOGO</i>	<i>File Name</i>
Windows 98 (E) Windows 98 (J)	English	2.80	-	W98_280.zip
Windows NT 4.0 (E) Windows NT 4.0 (J)	English	2.80	-	W98_280.zip
Windows 2000 (E) Windows 2000 (J)	English	2.80	-	W98_280.zip

Note: For Windows NT 4.0 Installation

- a) Open the installation folder or CD-ROM, and double-click on the "Setup.exe" icon. Follow the instructions on the Screen.
- b) When requested, replace the installation disks according to the instructions on the screen.
- c) You must choose a Communication port which will be used for your modem. It is recommended to choose port with number 3 or 4, because some old applications (16-bit) do not support a port higher than COM4.
- d) After files are copied, you will be asked to continue installation by standard Modem Installer.
- e) Click the "Next" button.

Because the modem is not yet installed, it can't be detected by the System. We recommend you to check "Do not detect my modem..." and select a modem from the list.


- f) Choose Manufacturer and Model from the list and press Next button.
Your Manufacturer is "CLEVO". Model is "HAMR56xxModem".
- g) Select your desired Communication Port.
- h) Reboot your computer.
The Modem setup is now finished.

 : The gray item means "New" driver.

1-16. B's Recorder Gold for CD-R/CD-RW (Option)

<i>Operation System</i>	<i>Support Font</i>	<i>Driver Version</i>	<i>PC99 LOGO</i>	<i>File Name</i>
Windows 98 (J)	Japanese	1.6	-	BS16.zip
Windows NT 4.0 (E) Windows NT 4.0 (J)	English Japanese			
Windows 2000 (E) Windows 2000 (J)	English Japanese			

Note: I.S/N:AL2F-BJJN-5935-9380

 : The gray item means "New" driver.